

	A	B	C	D	E	F	G	H	I	J	K	L	M	N	O	
17	日期	時間	台指指數	台指筆差	筆差變化											執行狀態
18	2021/2/5	08:01:08 PM	15808	-45												執行中
19	2021/2/5	6:27:00 PM	15807	-28												
20	2021/2/5	6:29:00 PM	15807	-31												
21	2021/2/5	6:30:00 PM	15807	-31												
22	2021/2/5	6:32:00 PM	15806	-38												
23	2021/2/5	6:33:00 PM	15807	-37												
24	2021/2/5	7:57:00 PM	15808	-44												
25	2021/2/5	7:58:00 PM	15808	-44												
26	2021/2/5	7:59:00 PM	15808	-44												
27	2021/2/5	8:00:00 PM	15808	-44												
28	2021/2/5	8:01:00 PM	15808	-45												

如何讓 D20-D19,自動輸入到 F21

D21-D20,自動輸入到 F22

以此類推

我的程式碼如下:

```
Sub 自動記載()  
If uMode = 0 Then Exit Sub  
If Time > TimeValue(EndT) Then  
    Sht1.[O18] = "已過收盤"
```

```
        uMode = 0
        Exit Sub
    End If
    Sht1.Range("B18") = Time
'-----
    If Second(Time) = 0 And Minute(Time) Mod 1 = 0 Then
        xRow = Sht1.Range("A65536").End(xlUp).Row + 1
        If xRow < 19 Then xRow = 19
        Sht1.Range("A" & xRow & ":N" & xRow).Value = Sht1.Range("A18:N18").Value
'-----
        If ActiveSheet.Name = Sht1.Name And xRow > 20 Then
            ActiveWindow.ScrollRow = xRow - 18
        End If
        ThisWorkbook.Save
        Beep
    End If
    Application.OnTime Now + TimeValue("00:00:01"), "自動記載"
End Sub
Sub  執行()
    If uMode = 1 Then Exit Sub
    Call  共用使用
    uMode = 1
    Sht1.[O18] = "執行中"
    Call  自動記載
End Sub
Sub  停止()
    uMode = 0
    Call  共用使用
    Sht1.[O18] = "停止中"
End Sub
Sub  清除()
```

```
Beep
If MsgBox("※確定要清除 [資料圖表區]的記錄嗎 ?", 4 + 32 + 256) = vbNo Then Exit Sub
Call 共用使用
Sht1.Rows("19:65536").ClearContents
If ActiveSheet.Name = Sht1.Name Then ActiveWindow.ScrollRow = 1
Beep
End Sub
```